

Esta «tabla» te ayudará a entender cada uno de los archivos que se alojan dentro de la base de datos config.db de un nodo de Proxmox (también conocida como **Proxmox Cluster File System** o **pmxcfs**, a secas):

```

/etc/pve/firewall/cluster.fw          # Firewall configuration applied to all nodes
/etc/pve/firewall/*.fw              # Firewall configuration for individual nodes
/etc/pve/firewall/*.fw              # Firewall configuration for VMs and containers
/etc/pve/ha/crm_commands             # Displays HA operations that are currently being carried out by
the CRM
/etc/pve/ha/manager_status           # JSON-formatted information regarding HA services on the cluster
/etc/pve/ha/resources.cfg           # Resources managed by high availability, and their current state
/etc/pve/local/                     # Enlace simbólico a /etc/pve/nodes/
/etc/pve/lxc/                        # Enlace simbólico a /etc/pve/nodes/NombreDelNodo/lxc/
/etc/pve/nodes/NombreDelNodo/lxc/*.conf # VM configuration data for LXC containers
/etc/pve/nodes/NombreDelNodo/opensvz/* # Prior to PVE 4.0, used for container configuration data
(Obsoleto)
/etc/pve/nodes/NombreDelNodo/priv/*
/etc/pve/nodes/NombreDelNodo/qemu-server/*.conf # VM configuration data for KVM VMs
/etc/pve/nodes/NombreDelNodo/pve-ssl.key      # Private SSL key for pve-ssl.pem
/etc/pve/nodes/NombreDelNodo/pve-ssl.pem     # Public SSL certificate for web server (signed by cluster CA)
/etc/pve/nodes/NombreDelNodo/pveproxy-ssl.key # Private SSL key for pveproxy-ssl.pem (optional)
/etc/pve/nodes/NombreDelNodo/pveproxy-ssl.pem # Public SSL certificate (chain) for web server (optional override
for pve-ssl.pem)
/etc/pve/nodes/NombreDelNodo/config         # Node-specific configuration
/etc/pve/opensvz/                         # Enlace simbólico a /etc/pve/nodes//opensvz/ (Obsoleto)
/etc/pve/priv/acme/*
/etc/pve/priv/lock/*                     # Lock files used by various services to ensure safe cluster-wide
operations
/etc/pve/priv/storage/*.pw              # Contains the password of a storage in plain text
/etc/pve/priv/authkey.key               # Private key used by ticket system
/etc/pve/priv/authorized_keys           # SSH keys of cluster members for authentication
/etc/pve/priv/ceph*                     # Ceph authentication keys and associated capabilities
/etc/pve/priv/known_hosts               # SSH keys of the cluster members for verification
/etc/pve/priv/pve-root-ca.key           # Private key of cluster CA
/etc/pve/priv/pve-root-ca.srl
/etc/pve/priv/shadow.cfg                 # Shadow password file for PVE Realm users
/etc/pve/priv/token.cfg                  # API token secrets of all tokens
/etc/pve/priv/tfa.cfg                    # Base64-encoded two-factor authentication configuration
/etc/pve/qemu-server/                   # Enlace simbólico a /etc/pve/nodes//qemu-server/
/etc/pve/sdn/*                           # Shared configuration files for Software Defined Networking (SDN)
/etc/pve/virtual-guest/cpu-models.conf   # For storing custom CPU models
/etc/pve/.clusterlog                     # Cluster log (last 50 entries)
/etc/pve/.debug
/etc/pve/.members                        # Info about cluster members
/etc/pve/.rrd                            # RRD data (most recent entries)
/etc/pve/.version                        # File versions (to detect file modifications)
/etc/pve/.vmlist                         # List of all VMs
/etc/pve/authkey.pub                     # Public key used by the ticket system
/etc/pve/ceph.conf                       # Ceph configuration file (note: /etc/ceph/ceph.conf is a symbolic
link to this)
/etc/pve/corosync.conf                   # Corosync cluster configuration file (prior to Proxmox VE 4.x,
this file was called cluster.conf)
/etc/pve/datacenter.cfg                  # Proxmox VE data center-wide configuration (keyboard layout,
proxy, ...)
/etc/pve/domains.cfg                     # Proxmox VE authentication domains
/etc/pve/pve-root-ca.pem                 # Public certificate of cluster CA
/etc/pve/pve-www.key                     # Private key used for generating CSRF tokens
/etc/pve/status.cfg                      # Proxmox VE external metrics server configuration
/etc/pve/replication.conf
/etc/pve/storage.cfg                     # Proxmox VE storage configuration
/etc/pve/user.cfg                        # Proxmox VE access control configuration (users/groups/...)
/etc/pve/vzdump.cron                     # Cluster-wide vzdump backup-job schedule

```

